

AmbiFi supports multiple levels of content depth, remember that content can be flat, in sections or lists and sections.

In addition we can also group items to provide a sub section look and feel for the user.

The screenshot displays the AmbiFi Training interface. On the left, a navigation pane shows a hierarchical structure:

- AmbiFi Training (blue header)
 - List 1 (blue list icon, highlighted with a red arrow)
 - Section 1 (orange section icon)
 - Item 1 (green checkmark icon)
 - Item 2 (green checkmark icon)
 - Item 3 (green checkmark icon)
 - Section 2 (orange section icon, collapsed with a plus sign)
 - Section 3 (orange section icon, collapsed with a plus sign)
 - List 2 (blue list icon, highlighted with a red arrow)
 - Section 1 (orange section icon)
 - Item 1 (green checkmark icon)

On the right, the configuration panel for 'AmbiFi Training' is shown:

- Presentation Mode:**
 - Procedure Mode (checked, green checkmark icon)
 - Show Mode (purple image icon)


Procedure Mode presents a hierarchy of information. All of the available Item Types are available in this mode.
- Activity Information:**
 - Title: AmbiFi Training
 - Don't Speak Title:
 - Genre: Miscellaneous
 - Description: (Optional: activity description)
- Drive Root Path:**

This will be the default location for quick uploads.

/private/activities/ ambifi-training
- Title Image:**
 - Image (camera icon)

Grouping items sometimes makes sense when they logically belong together and share a common header.

We will begin with creating some items and naming the items belonging in the group "Group Item 1-3"



To put items into a group we are utilizing group names.

#group-start is the group name that defines the start of a group

#group-end marks the group as completed

Note: We are working on UI enhancements to make this more visual and easier on the author, this is a new capability at the time of training.

We will start by adding the #group-start group name to "Group Item 1".

Select the item and expand "Advanced Options", then type the group name "#group-start" into the text box and hit ENTER when finished.

The screenshot displays a software interface with a left-hand navigation pane and a right-hand configuration pane. The left pane shows a list of items under the heading "AmbiFI Training". The items are: "List 1", "Timers", "Item Groups", "Section With Item Group", "My first check item", "Group item 1" (highlighted in blue), "Group item 2", "Group Item 3", and "My first check item after the group". A red arrow points to "Group item 1". The right pane shows configuration options for the selected item. The "Advanced Options" section is expanded and highlighted in green. A red arrow points to this section. Within "Advanced Options", there is a "Group Names" section with a text box containing "#group-start" and a placeholder "Enter a group name". A red arrow points to this text box. Other options in the "Advanced Options" section include "ID", "Filter Tags", "Don't Print", "Start Timer when Checked", "Stop Timer when Checked", "Start Tracking when Checked", "Stop Tracking when Checked", "Save On Complete (Check)", "Save And Exit On Complete (Check)", and "Generate Report On Complete (Check)". There are also "Start Named Timers" and "Stop Named Timers" sections, each with a text box and a dropdown arrow. At the bottom, there is a "Label 1" section with a dropdown arrow.


Next we still need to add the "#group-end" group name to end the group at "Group Item 3"

Once again, select the item (Group Item 3) and expand "Advanced" then enter "#group-end" into the group name text box and hit ENTER when finished.

The screenshot displays the Ambifl Training software interface. On the left, a sidebar lists various items, with "Group Item 3" selected and highlighted in blue. A red arrow points to this item. On the right, the "Advanced Options" panel is expanded, indicated by a red arrow. Within this panel, the "Group Names" section contains a text input field with "#group-end" entered and a red arrow pointing to it. Below this, several checkboxes are visible, including "Don't Print", "Start Timer when Checked", "Stop Timer when Checked", "Start Tracking when Checked", "Stop Tracking when Checked", "Save On Complete (Check)", "Save And Exit On Complete (Check)", and "Generate Report On Complete (Check)". At the bottom of the panel, there are dropdown menus for "Start Named Timers" and "Stop Named Timers", and a "Label 1" section.

Since this is a new feature please use your mobile device to preview the item group.

Notice how there is a border drawn around the items, grouping them and indenting them some.



We also have the ability to add a header to a group, this is accomplished by adding a "Label Only" Check Item and making it the first item in the group.

Add a new check item and move it (using the up and down arrows) just above the "Group Item 1", remove the #group-start group name from "Group Item 1" and add it to the header item instead (it must be the first item).

The screenshot displays a software interface with a list of items on the left and a detailed configuration panel on the right. The list includes:

- AmbiFI Training
- List 1
- Timers
- Item Groups
- Section With Item Group
- My first check item
- Group Header** (highlighted in blue, with "Groups: #group-start" below it)
- Group item 1
- Group item 2
- Group Item 3 (with "Groups: #group-end" below it)
- My first check item after the group

The detailed view for the "Group Header" item shows the following configuration:

- Check Item**: A text input field.
- Label Only**: A checked checkbox.
- Navigation Title**: A section with a subtitle "A shorter title for this item that will be shown in navigation." and a text input field containing "(Navigation Title)".
- Don't Show In Navigation Tree View**: An unchecked checkbox.
- Label 1**: A section with a text input field containing "Group Header" and an unchecked checkbox "Don't Speak Label 1".
- Preview**: A section with the text "Group Header".
- Label 2**: A section with a text input field containing "(Optional: Label 2)" and an unchecked checkbox "Don't Speak Label 2".
- Media**: A section with a dropdown arrow.
- Comments**: A section with an "Add Comments" button and a comment icon.

Red arrows indicate the following actions:

- An arrow points from the "Group Header" item in the list to the "Label Only" checkbox in the configuration panel.
- An arrow points from the "Group Header" item in the list to the "Group Header" text in the "Label 1" field.

Once this has been completed refresh the activity on the mobile device (iPhone or iPad) again and you will see the new group header.

Note: Styling of the header is very flexible and follows the same rules as any item, the header is not considered part of the activity and will not be tracked.

